January 1, 2003

LONGLINE GEAR LOG

This log contains detailed questions about the gear fished. Generally one gear is used to describe gear within a single trip. Changes in item numbers used would not require a separate gear log, however a change in gear configuration (i.e. use of light sticks, hooks between floats or fishing depth)that redirects toward another target species would require a separate gear log. Numeric values reflect an average from all hauls with the same string number.

Example: First two hauls use light sticks and direct toward swordfish described by string number 1. The remaining five hauls do **not** use light sticks and target tuna. A second gear log would then be completed and numbered string number 2. Record the appropriate string number in **field #16** on each of the <u>LONGLINE HAUL LOG</u> sheets. Hauls 1-2=1 and Hauls 3-7=2

If information is not available or unknown for any question except a "NO/YES" question, record a dash (-) in the field. If the answer to a "NO/YES" question is unknown, record a "9", instead of an "X", on the line next to the code "NO=0".

DEFINITIONS

LONGLINE: 600-1000 lb test monofilament nylon mainline ("string") supported in the water column by floats "droplines", and having attached branch lines "gangions" which have baited hooks on the free end.

<u>SECTION</u>: A portion of a string with an arrangement of floats, hooks and polyballs defined on either end by a radar reflector or radio beacon. Generally section configuration is repeated throughout a string with some variation occurring in the last section set.

GANGION: A 300-500 lb test nylon monofilament attached to a mainline by a snap. A gangion may vary in length and have up to two swivels, one at the snap and another some distance above the hook. Fishers may refer to this as a "leader".

<u>LEADER</u>: A section of mono or steel wire placed between a swivel and the hook. It reduces bite offs, makes hook replacement easier and helps to maintain the gangion length. Fishers may refer to this as a "tail".

<u>DROPLINE</u>: A 300-500 lb nylon monofilament or braided nylon line connecting the float to the mainline. Fishers may refer to this as a "drop" or float line.

INSTRUCTIONS

HEADER

- 1. <u>OBS/TRIP ID</u>: Record the three character observer/trip identifier. This should be used on all data forms and field notes for a single trip.

 Example: A12.
- 2. <u>VESSEL NAME</u>: Record the name of the vessel. Care should be taken to record the correct spelling of the vessel's name. Do not use punctuation; hyphens, commas, or periods and data is entered in capital letters. Example: MR ROGERS, SY KAI MAI, MISSYS DREAM
- 3. <u>VESSEL NUMBER</u>: Record the six digit U.S. Coast Guard Documentation Number. This should be displayed prominently on the vessel. If the vessel does not have a Coast Guard Number, record the state registration number and include the two letter state abbreviation prefix. This is not the same as the NMFS or state fishing permit number.

Example: USCG documentation number - 234567 State registration number - FL2345XX

- 4. <u>DATE LANDED</u>: Record the month, day and year when the vessel arrives back in port. This may not be the same day fish are unloaded and sold. Example: 01/01/2003
- 5. <u>STRING NUMBER</u>: Record the consecutive number assigned to each string as it is uniquely configured. Changes that result in a change in target species will necessitate a new number and <u>LONGLINE GEAR LOG</u>. Each string will be assigned a number consecutively, i.e., first string = 1, the next string = 2, etc.

GEAR INFORMATION

- 6. <u>NUMBER OF HOOKS</u>: Record the number of hooks set. This is an **average** of all hauls with the same gear configuration.
- 7. <u>ANCHOR USED?</u>: Indicate if an anchor was used, by placing an "X" next to the appropriate code: **NO=0** YES=1
- 8. <u>WEIGHT</u>: Record an estimated total weight, to the nearest pound, of the anchor(s) used to hold the gear in place. This information can be obtained from the captain. If no

anchor was used or if the gear is tied directly to the vessel, enter "0".

MAINLINE

9. <u>COLOR</u>: Record the color of the main line, by placing an "X" next to the appropriate code. If more than one color is present place an "X" next those colors present and a "07" will be entered into the database.

Please describe other colors in field #43 COMMENTS.

- 10. <u>NUMBER OF STRANDS</u>: Record the number of strands of material that make up the mainline. Generally this should be "1".
- 11. <u>DIAMETER</u>: Record, to the nearest tenth of a millimeter, the diameter of the mainline. Use a caliper, if provided or submit a label or sample piece with your data. General ranges found are 3.0-4.2 mm
- 12. <u>TEST</u>: Record the pound test or dry breaking strength of the main line. This information can obtained from the captain and/or verified from a manufacturer label. General ranges found are 600-1000 lbs.
- 13. <u>MATERIAL</u>: Indicate the material that the mainline is constructed of, by placing an "X" next to the appropriate code:

Please describe other materials in field #43 COMMENTS.

FLOATS

14. <u>TYPE USED?</u>: Indicate whether a float type was used, by placing a "0" or "1" in the space provided: NO=0 **YES=1**

Polyball Bullet/Daub Other

Please describe other float type in field #42 COMMENTS.

- 15. <u>TYPE NUMBER</u>: Record the number for each float type used. This is an **average** of all hauls with the same gear configuration.
- 16. <u>MAX HOOK BETWEEN</u>: Record the **maximum** number of hooks between bullet/daub floats. This is an **average** of all hauls with the same gear configuration.
- 17. <u>RADIO BEACONS</u>: Record the number of radio beacons. These may also be called "radio buoys" or "beepers". This is an **average** of all hauls with the same gear configuration.
- 18. RADAR REFLECTORS: Record the number of radar reflectors. These may also be called "highfliers". This is an **average** of all hauls with the same gear configuration.
- 19. <u>SECTIONS</u>: Record the number of sections. This is an **average** of all hauls with the same gear configuration.
- 20. <u>DISTANCE BETWEEN SECTIONS</u>: Record the distance to the nearest tenth of a nautical mile. This is an **average** of all hauls with the same gear configuration.

LIGHT STICKS

- 21. <u>LIGHT STICKS USED?</u>: Indicate whether light sticks are used on this string by placing an "X" next to the appropriate code: NO=0 **YES=1**
- 22. <u>LIGHT STICK COLOR</u>: Indicate the color or colors of light sticks used on this string by placing an "X" next to the appropriate code. If there is more than one color a code 07 (multi-color) will be entered into the database.

GANGIONS

- 23. <u>COLOR</u>: Indicate the color of the gangion line by placing an "X" next to the appropriate code.
 - Please record any other color in field #42 COMMENTS.
- 24. <u>DISTANCE BETWEEN</u>: Record the distance, in whole feet, between gangions. This is an **average** of all hauls with the same gear configuration.
- 25. <u>DIAMETER</u>: Record, to the nearest tenth of a millimeter, the diameter of the gangions. General ranges found are 1.8-2.2 mm
- 26. <u>TEST</u>: Record the pound test or dry breaking strength of the gangions. General ranges found are **300-500 lbs**.
- 27. MATERIAL: Indicate the material that is used for the gangions by placing an "X" next to the appropriate code:

 Nylon = 1, Cotton = 2, Steel Wire = 3, Other = 9
 - Please record other material in field #42 COMMENTS.
- 28. <u>GANGION LENGTH</u>: Record, to the nearest foot, the gangion lengths. You can account for up to two different lengths. Gangion length should not include the leader length. This is an **average** of all hauls with the same gear configuration.
- 29. <u>GANGION COUNT</u>: Record the number of gangions for each length used. This is an **average** of all hauls with the same gear configuration.
- 30. <u>LEADERS USED?</u>: Indicate whether leaders are used between the gangion and the hook by placing a "0" or "1" in the space provided: NO=0 **YES=1**
- 31. <u>LEADER LENGTH</u>: Record the length of the leader to nearest **inch**. This is an **average** of all hauls with the same gear configuration.
- 32. <u>LEADER TEST</u>: Record the pound test or dry breaking strength of the leader. Generally this is the same as the gangion.
- 33. <u>LEADER MATERIAL</u>: Indicate the leader material by placing an "X" next to the appropriate code. **Nylon = 1**, Cotton = 2, Steel Wire = 3, Other = 9. Please record **other** material in field #42 **COMMENTS**.

- 34. <u>SWIVELS USED?</u>: Indicate whether swivels are used on gangions by placing a "0" or "1" in the space provided: NO=0 **YES=1**
- 35. <u>NUMBER SWIVELS/ GANGION</u>: Record the number of swivels used per gangion. One is generally located at the snap and a second swivel will be located some distance above the hook between the gangion and the leader.

DROPLINES

- 36. <u>LENGTH</u>: Record, to the nearest foot, the length of the droplines. This is an **average** of all hauls with the same gear configuration.
- 37. <u>DISTANCE BETWEEN</u>: Record, to the nearest foot, the distance between droplines. This is an **average** of all hauls with the same gear configuration.
- 38. <u>HOOK BRAND</u>: Record the hook brand name. You can account for up to three different hooks. This information can be obtained from the captain and/or verified from a manufacturer label or Hook Guide. Example: Mustad, Eagle Claw, LGPN (Lundgren/Pittman)
- 39. MODEL/PATTERN: Record the hook model or pattern number. You can account for up to two different hooks. This information can be obtained from the captain and/or verified from a manufacturer label or Hook Guide. DO NOT include LETTERS in this field. Example: 7698B=7698, L9015=9015, 9014CAT=9014
- 40. <u>SIZE</u>: Record the hook size. You can account for up to three different hooks. This information can be obtained from the captain and/or verified from a manufacturer label or Hook Guide.

 Example: 9/0
- 41. <u>COMMENTS</u>: Indicate whether additional information concerning the gear was recorded, by placing an "X" next to the appropriate code: NO=0 YES=1. Please reference each comment with its corresponding field number. If more space is required, use the back of the sheet and include "see back" on the front. Comments will be entered into a MEMO field in the database when the code = 1.